

Using VoiceOver: Basic Commands/Finger Gestures

Using VoiceOver Unlock iPad: Select the Unlock button, then double-tap the screen.

Select items on the screen: Drag your finger across the screen.

VoiceOver identifies each element as you touch it.

You can also move systematically from one element to the next by flicking left or right with one finger.

Elements are selected from left to right, top to bottom.

Flick right to go to the next element, or flick left to go to the previous element.

“Tap” a selected item when VoiceOver is turned on: Double-tap anywhere on the screen.

Speak the text of an element, character-by-character, word-by-word, or line-by-line: With the element selected, flick up or down with one finger.

Flick down to read the next character, or flick up to read the previous character.

Twist the rotor control to read word-by-word or line-by-line.

Adjust a slider: With one finger, flick up to increase the setting or down to decrease the setting. VoiceOver speaks the setting as you adjust it.

Scroll a list or area of the screen: Flick up or down with three fingers.

Flick down to page down, or flick up to page up. When paging through a list, VoiceOver speaks the range of items displayed (for example, “showing rows 5 through 10”).

Scroll continuously through a list: Double-tap and hold. When you hear a series of tones, you can move your finger up or down to scroll the list. Continuous scrolling stops when you lift your finger.

Use an index: Some lists have an alphabetical index along the right side. The index can't be selected by flicking between elements; you must tap the index to select it. With the index selected, flick up or down to move along the index. You can also double-tap, then slide your finger up or down.

Rearrange the Home screen: On the Home screen, select the icon you want to move. Double-tap and hold, then drag the icon. VoiceOver speaks the row and column position as you drag the icon. Release the icon when it's in the location you want. You can drag

additional icons. Drag an item to the left or right edge of the screen to move it to a different page of the Home screen. When you finish rearranging the icons, press the Home button. You can turn speaking off, stop speaking an item, turn the display off, or have VoiceOver speak the entire screen.

Mute VoiceOver: Double-tap with three fingers. Double-tap with three fingers again to turn speaking back on. To mute only VoiceOver sounds, set the Side Switch to silent.

Stop speaking an item: Tap once with two fingers. Tap again with two fingers to resume speaking. Speaking automatically resumes when you select another item.

Turn off the display while you use VoiceOver: Triple-tap with three fingers. Repeat to turn the display on again.

Speak the entire screen from the top: Flick up with two fingers.

Speak from the current item to the bottom of screen: Flick down with two fingers.